Thunderbird 115 Set up

When you are configuring an email account, Thunderbird will often be able to do most of the configuration automatically. However, you will need to manually configure your account if using SpinTel Email Settings.

- 1. Open Mozilla Thunderbird.
- 2. Click **Tools** or click the Application menu button.
- 3. Select Account Settings.



- 4. At the bottom of the left pane, click Account Actions.
- 5. Select Add Mail Account.



- 6. Enter your email account details and press **Continue**.
 - Your Name: Enter your full name (or the name you'd like people to see when you send them email from this account).
 - Email Address: Enter the SpinTel email address you're setting up.
 - **Password**: Enter the password for the email address you're setting up.

		i
mail address		
		(i)
assword	Get a new	email address
Remember password		
Remember password	Cancel	Continue

7. Press **Manual Configuration** and edit the server names, ports, and IMAP/POP to manually set up the account. IMAP synchronizes the email on your computer with the contents of your account on the server, while POP simply downloads the inbox.

Fill in the following information depending on the incoming protocol you chose:

POP

- Incoming: **POP**
- Server Hostname: **pop3.spintel.net.au**
- Port: **110** (default pop3 port)

995 (Port used for SSL/TLS)

- SSL (Optional): Enabled (recommended)
- Outgoing Server Authentication: Enabled
- Outgoing Server: smtp.spintel.net.au
- Port: **587**

465 with SSL enabled)

• Username: Enter your username (without @spin.net.au)

Email address:							
Password:	Remen	nber password					
		Server hostname	Port SS	il.		Authentication	
Incoming:	POP Y	_ pop3.spintel.net.au _	· · · ·	and the second s	~		
Outgoing:	SMTP	smtp.spintel.net.au 🖌	¥		~	Er.	
		Your username					
Username:							

IMAP

- Incoming: **IMAP**
- Server Hostname: imap.spintel.net.au

- Port: 143 (Default IMAP port. Also used for TLS)
 993 IMAP port used for SSL
- SSL (Optional): Enabled Recommended
- Outgoing Server Authentication: Enabled
- Outgoing Server: **smtp.spintel.net.au**
- Port: **587**

465 *with SSL enabled*)

• Username: Enter your username (without @spin.net.au)

									imai <u>l</u> address:
								:	Password:
						ssword	ember passwor	Remer	
1	Authenticatio	A		SSL	Port	hostname	Server hostn		
		•	-		· · · ·	ap.spintel.net.au	imap.s	IMAP v	Incoming:
		¥			×	tp.spintel.net.au	smtp.s	SMTP	Outgoing: S
]	our username	Your		Username:
		•			v	tp.spintel.net.au our username	smtp.s	SMTP	Outgoing: S Username:

8. Click Done/Create Account.

9. Wait for the mail client to finish verifying the email settings.

10. Complete! You should be able to send and receive emails.

Online URL: https://articles.spintel.net.au/article/thunderbird-115-set-up.html