


Thunderbird 115 Set up


When you are configuring an email account, Thunderbird will often be able to do most of the configuration automatically. However, you will need to manually configure your account if using SpinTel Email Settings.

1. Open **Mozilla Thunderbird**.
2. Click **Tools** or click the Application menu button.
3. Select **Account Settings**.



4. At the bottom of the left pane, click **Account Actions**.

5. Select **Add Mail Account**.



6. Enter your email account details and press **Continue**.

- **Your Name:** Enter your full name (or the name you'd like people to see when you send them email from this account).
- **Email Address:** Enter the SpinTel email address you're setting up.
- **Password:** Enter the password for the email address you're setting up.

Your full name

Email address

[Get a new email address](#)

Password

Remember password

Your credentials will only be stored locally on your computer.

7. Press **Manual Configuration** and edit the server names, ports, and IMAP/POP to manually set up the account. IMAP synchronizes the email on your computer with the contents of your account on the server, while POP simply downloads the inbox.

Fill in the following information depending on the incoming protocol you chose:

POP

- Incoming: **POP**
- Server Hostname: **pop3.spintel.net.au**
- Port: **110** (default pop3 port)

995 (Port used for SSL/TLS)

- SSL (Optional): **Enabled (recommended)**
- Outgoing Server Authentication: **Enabled**
- Outgoing Server: **smtp.spintel.net.au**
- Port: **587**

465 with SSL enabled)

- Username: Enter your username (without @spin.net.au)

The screenshot shows a configuration window for an email account. It includes fields for 'Your name', 'Email address', and 'Password', with a 'Remember password' checkbox. Below these is a table for server settings:

	Server hostname	Port	SSL	Authentication
Incoming:	POP	pop3.spintel.net.au		
Outgoing:	SMTP	smtp.spintel.net.au		
Username:	Your username			

At the bottom, there are buttons for 'Get a new account', 'Advanced config', 'Re-test', 'Done', and 'Cancel'.

IMAP

- Incoming: **IMAP**
- Server Hostname: **imap.spintel.net.au**

- Port: **143** (Default IMAP port. Also used for TLS)
993 – IMAP port used for SSL
- SSL (Optional): **Enabled Recommended**
- Outgoing Server Authentication: **Enabled**
- Outgoing Server: **smtp.spintel.net.au**
- Port: **587**
465 with SSL enabled)
- Username: Enter your username (without @spin.net.au)

The screenshot shows an email account configuration window. It includes the following elements:

- Your name:** [Text input field] Your name, as shown to others
- Email address:** [Text input field]
- Password:** [Text input field]
- Remember password**
- Incoming:** IMAP (dropdown), **imap.spintel.net.au** (Server hostname), [Port dropdown], [SSL dropdown], [Authentication dropdown]
- Outgoing:** SMTP, **smtp.spintel.net.au** (Server hostname), [Port dropdown], [SSL dropdown], [Authentication dropdown]
- Username:** [Text input field] Your username
- Buttons:** Get a new account, Advanced config, Re-test, Done, Cancel

8. Click **Done/Create Account**.

9. Wait for the mail client to finish verifying the email settings.

10. Complete! You should be able to send and receive emails.

Online URL: <https://articles.spintel.net.au/article/thunderbird-115-set-up.html>