


Thunderbird 115 Set up




When you are configuring an email account, Thunderbird will often be able to do most of the configuration automatically. However, you will need to manually configure your account if using SpinTel Email Settings.

1. Open **Mozilla Thunderbird**.
2. Click **Tools** or click the Application menu button.
3. Select **Account Settings**.




4. At the bottom of the left pane, click **Account Actions**.

5. Select **Add Mail Account**.



6. Enter your email account details and press **Continue**.

- **Your Name:** Enter your full name (or the name you'd like people to see when you send them email from this account).
- **Email Address:** Enter the SpinTel email address you're setting up.
- **Password:** Enter the password for the email address you're setting up.



Your full name

Email address

Get a new email address

Password

Remember password

Cancel Continue

Your credentials will only be stored locally on your computer.

7. Press **Manual Configuration** and edit the server names, ports, and IMAP/POP to manually set up the account. IMAP synchronizes the email on your computer with the contents of your account on the server, while POP simply downloads the inbox.

Fill in the following information depending on the incoming protocol you chose:

POP

- Incoming: **POP**
- Server Hostname: **pop3.spintel.net.au**
- Port: **110** (default pop3 port)

995 (Port used for SSL/TLS)

- SSL (Optional): **Enabled (recommended)**
- Outgoing Server Authentication: **Enabled**
- Outgoing Server: **smtp.spintel.net.au**
- Port: **587**

465 with SSL enabled)

- Username: Enter your username (without @spin.net.au)

The screenshot shows an email client configuration window with the following fields and options:

- Your name:** [Text input field] Your name, as shown to others
- Email address:** [Text input field]
- Password:** [Text input field]
- Remember password**
- Incoming:** POP (dropdown), Server hostname: pop3.spintel.net.au, Port: [dropdown], SSL: [dropdown], Authentication: [dropdown]
- Outgoing:** SMTP, Server hostname: smtp.spintel.net.au ✓, Port: [dropdown], SSL: [dropdown], Authentication: [dropdown]
- Username:** [Text input field] Your username
- Buttons:** Get a new account, Advanced config, Re-test, Done, Cancel

IMAP

- Incoming: **IMAP**
- Server Hostname: **imap.spintel.net.au**

- Port: **143** (Default IMAP port. Also used for TLS)
993 – IMAP port used for SSL
- SSL (Optional): **Enabled Recommended**
- Outgoing Server Authentication: **Enabled**
- Outgoing Server: **smtp.spintel.net.au**
- Port: **587**
465 with SSL enabled)
- Username: Enter your username (without @spin.net.au)

The screenshot shows an email account configuration window. It includes the following elements:

- Your name:** [Text input field] Your name, as shown to others
- Email address:** [Text input field]
- Password:** [Text input field]
- Remember password
- Incoming:** IMAP (dropdown), Server hostname: **imap.spintel.net.au**, Port: [dropdown], SSL: [dropdown], Authentication: [dropdown]
- Outgoing:** SMTP, Server hostname: **smtp.spintel.net.au**, Port: [dropdown], SSL: [dropdown], Authentication: [dropdown]
- Username:** [Text input field] **Your username**
- Buttons at the bottom: **Get a new account**, **Advanced config**, **Re-test**, **Done**, **Cancel**

8. Click **Done/Create Account**.

9. Wait for the mail client to finish verifying the email settings.

10. Complete! You should be able to send and receive emails.

Online URL: <https://articles.spintel.net.au/article/thunderbird-115-set-up.html>